

Software Manual Windows Driver

Rev. 3.03 SLP-TX220 / TX223 SLP-TX420 / TX423 SLP-DX220 / DX223 SLP-DX420 / DX423 SLP-DL410 / DL413 SLP-T400 / T403 SLP-T400R / T403R SLP-D220 / D223 SLP-D420 / D423 SRP-770II / 770III

Table of Contents

1. Manual Information	3
2. Operating System (OS) Environment	3
3. Windows Driver Preparation	3
4. Windows Driver Installation	4
4-1 Installing on Windows XP/Server 2003	4
4-1-1 Via Serial or Parallel Port	4
4-1-2 Via USB Port	8
4-1-3 Via Network Port	14
4-2 Installing Windows VISTA/Server 2008/7/8/Server 2012/10	18
4-2-1 Via Serial or Parallel Port	18
4-2-2 Via USB Port	22
4-2-3 Via Network Port	26
5. Detailed Windows Driver Settings	
5-1 Printing Preferences	
5-2 Adding new paper size	31
6. Specifications	33
6-1 Resolution	
6-2 Paper Size	33

1. Manual Information

This Windows Driver Installation Manual provides information on installation, detailed specifications, and usage of the printer's Windows Driver according to PC operating system (OS).

We at BIXOLON maintain ongoing efforts to enhance and upgrade the functions and quality of all our products. In following, product specifications and/or user manual content may be changed without prior notice.

2. Operating System (OS) Environment

The following operating systems are supported for usage.

Microsoft Windows XP SP3 (32bit, 64bit) Microsoft Windows Server 2003 SP1 (32bit) Microsoft Windows Server 2003 (64bit) Microsoft Windows VISTA (32bit, 64bit) Microsoft Windows Server 2008 (32bit, 64bit) Microsoft Windows Server 2008 R2 (64bit) Microsoft Windows 7 (32bit, 64bit) Microsoft Windows 8 (32bit, 64bit) Microsoft Windows 8 (32bit, 64bit) Microsoft Windows 10 (32bit, 64bit)

3. Windows Driver Preparation

The Windows Driver is included in the enclosed CD, and Latest file versions can be downloaded from the BIXOLON website. (www.bixolon.com)

4. Windows Driver Installation

4-1 Installing on Windows XP/Server 2003

- 4-1-1 Via Serial or Parallel Port
- 1) Double-click the Windows Driver installation file.
- 2) Click the "Next" button.

BIXOLON LABEL PRINTER		×
BIXOLON LABEL PRINTER	Welcome to the InstallShield Wizard for SLP-XXxx0 Windows driver The InstallShield Wizard will install SLP-XXxx0 Windows driver on your computer. To continue, click Next.	
InstallShield	< Back Next> Cancel	

Windows Driver

 Select the COM or LPT (Which one you want to use) port to be used and click the "Next" button.

Select a printer and port		BIXOLON
Manufacturer BXOLON	Printers BIXOLON SLP- BIXOLON SLP-	XXXxx0 XXXxx3
Serial Port © COM1 © COM3 © COM2 © COM4	Parallel Port O LPT1 O LPT2	USB Port O USB
Network Port	192 . 168 . 1 . 1	Port : 9100
Cancel		Next

Select a printer and port		BIXOLON
Manufacturer BIXOLON	Printers BIXOLON SLP BIXOLON SLP	-X0xx0 -X0xx3
Serial Port COM1 COM3 COM2 COM4	Parallel Port ③ LPT1 ③ LPT2	USB Port O USB
Network Port	192 . 168 . 1 . 1	Port : 9100
Cancel		Next

4) When the following message box appears, click the "Continue Anyway" button.



5) Clicking the "Yes" button will reboot the PC.



- 6) Open the printer properties window in the Windows OS.
- 7) Click the "Port Settings" button in the "Ports" tab.

IIXOLON SLP-XXxx0 Properties
Stocks Language Barcode Fonts Command Fonts About General Sharing Ports Advanced Printer Settings Image: State of the state
Port Description Printer LPT1: Printer Port LPT2: Printer Port LPT3: Printer Port COM1: Serial Port COM2: Serial Port COM4: Serial Port COM4: Serial Port Add Port Delete Port Configure Port Y Enable bidirectional support Enable printer pooling
OK Cancel Apply Help

Windows Driver

8) Match the communication settings to those of the printer.

(The communication settings of the printer can be performed by conducting a self-test.)

COM1 Properties	? 🛛
Port Settings	
<u>B</u> its per second:	115200
<u>D</u> ata bits:	8
<u>P</u> arity:	None
<u>S</u> top bits:	1
Elow control:	Hardware
	<u>R</u> estore Defaults
	K Cancel Apply

9) Click the "Print Test Page" button and check printing status.

Stocks	Language	Barcode	Fonts	Comman	d Fonts Ab	out
General	Sharing	Ports	Ad	ivanced	Printer Settin	igs
S	BIXOLON	SLP-XXxx	0			
Location:						
Comment:						٦
Model:	BIXOLON	SLP-XXxx	0			-
Features						-
Color: No	(P	aper av	ailable:		
Double-sided: No Staple: Unknown Speed: Unknown Maximum resolution: 203 dpi		L B B B B B B B B B B B B B B B B B B B	Iser defi XOLON XOLON XOLON XOLON	ned N 1.5 x 1.0 (N 1.5 x 1.5 (N 1.5 x 2.0 (N 2.0 x 1.0 (N 2.0 x 1.5 (inch) inch) inch) inch) inch)	
	(Printing Pre	ference	s) P	iint Test Page	

10) Proper installation of the driver is indicated if the test page is printed normally.

4-1-2 Via USB Port

- 1) Double-click the Windows Driver installation file.
- 2) Click the "Next" button.



3) Select USB and click the "Next" button.

Select a printer and port		BIXOLON
Manufacturer	Printers BIXOLON SLE BIXOLON SLE	P-XXxx0 P-XXxx3
Serial Port COM1 COM3 COM2 COM4	Parallel Port O LPT1 O LPT2	USB Port
Network Port	92 . 168 . 1 . 1	Port: 9100
Cancel		Next

4) When the following message box appears, click the "Continue Anyway" button.



5) Click the "OK" button.



6) Turn on the printer.

7) When the New Hardware Wizard appears for the installation of the Windows Driver, select the option as shown below and click the "Next" button.



8) Click the "Next" button.

Found New Hardware Wiz	ard
	This wizard helps you install software for: BIXOLON SLP-XXxx0
	If your hardware came with an installation CD or floppy disk, insert it now.
	What do you want the wizard to do? Install the software automatically (Recommended) Install from a list or specific location (Advanced) Click Next to continue
	< Back Next > Cancel

9) Click the "Next" button.

Found New Hardware Wizard		
Please wait while the wizard installs t	he software	Ð
BIXOLON SLP-XXXX0		
iii - 2		
	K Back Next >	Cancel

10) Click the "Continue Anyway" button.

Hardwa	re Installation
	The software you are installing for this hardware: Printers has not passed Windows Logo testing to verify its compatibility with Windows XP. (<u>Tell me why this testing is important</u> .) Continuing your installation of this software may impair or destabilize the correct operation of your system either immediately or in the future. Microsoft strongly recommends that you stop this installation now and contact the hardware vendor for software that has passed Windows Logo testing.
	Continue Anyway

11) Click the "Finish" button.



12) The USB Port setting can be confirmed in the Windows Driver properties.

BIXOLON	SLP-XXxx0 Prope	rties		ľ	2
Stocks General	Language Barcoo Sharing Ports	le Fonts S Ac	Command Ivanced	Fonts Abo Printer Settin	out gs
Print to the fr	DLON SLP-XXXX0	nents will n	int to the fire	st free	-
Port	Description	Prir	nter	2	
	Serial Port Serial Port Serial Port				
	Print to File 11 Virtual printer port	fo BIX	OLON SL	P-XXxx0	
Add P	or <u>t D</u> e directional support	lete Port		onfigure Port	
Enable pr	inter pooling				
(ок с	ancel	Apply	Help	n i

13) Click the "Print Test Page" button and check printing status.

Stocks	Language B	arcode Fonts	Comman	d Fonts	About
General	Sharing	Ports 4	Advanced	Printer	Settings
S	BIXOLON SL	P-XXxx0			
Location:					
Comment:					-
Modelt	BIXOLON SL	P-XXxx0			
Features					-
Color: No		Paper a	vailable:		
Double-si Staple: U Speed: U Maximum	ided: No nknown Inknown resolution: 203 dj	User de BIXOLO BIXOLO BIXOLO BIXOLO BIXOLO	fined DN 1.5 x 1.0 (i DN 1.5 x 1.5 (i DN 1.5 x 2.0 (i DN 2.0 x 1.0 (i DN 2.0 x 1.5 (i	inch) inch) inch) inch)	×
	Prin	nting Preferenc	es) P	nin t Test P	age

14) Proper installation of the driver is indicated if the test page is printed normally.

- 4-1-3 Via Network Port
- 1) Double-click the Windows Driver installation file.
- 2) Click the "Next" button.



- 3) Select Network port.
- 4) Type IP address and port number and then click "Next" button.

Select a printer a	nd port			BIXOLON
Manufacturer — BIXOLON			Printers BIXOLON SLP BIXOLON SLP	-XXXxX0 -XXXxX3
Serial Port O COM1 O COM2	○ СОМЗ ○ СОМ4		Parallel Port O LPT1 O LPT2	USB Port O USB
Network Port	IP :	192	. 168 . 1 . 1	Port : 9100
Cancel				Next

5) When the following message box appears, click the "Continue Anyway" button.

Hardwa	re Installation
1	The software you are installing for this hardware: Printers has not passed Windows Logo testing to verify its compatibility with this version of Windows. (Tell me why this testing is important) Continuing your installation of this software may impair or destabilize the correct operation of your system either immediately or in the future. Microsoft strongly recommends that you stop this installation now and contact the hardware vendor for software that has passed Windows Logo testing.
	Continue Anyway STOP Installation

6) Clicking the "Yes" button will reboot the PC.



7) Open the printer properties window in the Windows OS.

8) Click the "Port Settings" button in the "Ports" tab.

SIXOLON SLP-XXxx0 Properties	? 🗙
Stocks Language Barcode Fonts Command Fonts About the second secon	out igs
Print to the following port(s). Documents will print to the first free checked port.	
Port Description Printer 🦉	~
COM4: Serial Port FILE: Print to File USB Virtual printer port fo TPVM: ThinPrint Print Port f	
IP_1 Standard TCP/IP Port BIXOLON SLP-XXxx0	
□ XPS Local Port Microsoft XPS Document Wr	
Add Port Delete Port Configure Port	
OK Cancel Apply Help	p

9) Match the communication settings to those of the printer.

Configure Standard TCP/IP Po	ort Monitor 🛛 🛛 🛛 💽
Port Settings	
Port Name:	IP_192.168.1.1
Printer Name or IP Address:	192.168.1.1
Protocol	◯ LPR
Raw Settings Port Number: 9100	
LPR Settings Queue Name:	
LPR Byte Counting Enabled	
SNMP Status Enabled	
Community Name: public	
SNMP Device Index: 1	
	OK Cancel

10) Click the "Print Test Page" button and check printing status.

Stocks	Language Baro	ode Fonts	Comman	d Fonts	About
General	Sharing Po	orts 🛛 🗛	dvanced	Printer	Settings
S	BIXOLON SLP-	XXXX0			
Location:					
Comment:					
Model:	BIXOLON SLP-	XXxx0			
Features					
Color: No	(Paper av	ailable:		
Double-si Staple: U Speed: U Maximum	ided: No nknown Inknown resolution: 203 dpi	User defi BIXOLOI BIXOLOI BIXOLOI BIXOLOI BIXOLOI	ined N 1.5 x 1.0 (N 1.5 x 1.5 (N 1.5 x 2.0 (N 2.0 x 1.0 (N 2.0 x 1.5 (inch) inch) inch) inch) inch)	< >
	Printin	g Preference	s) P	rint Test P	age

11) Proper installation of the driver is indicated if the test page is printed normally.

4-2 Installing Windows VISTA/Server 2008/7/8/Server 2012/10

- 4-2-1 Via Serial or Parallel Port
- 1) Double-click the Windows Driver installation file.
- 2) Click the "Yes" button.



3) Click the "Next" button.

BIXOLON LABEL PRINTER		×
BIXOLON LABEL PRINTER	Welcome to the InstallShield Wizard for SLP-XXxx0 Windows driver InstallShield Wizard will install SLP-XXxx0 Windows driver on your computer. To continue, click Next.	
InstallShield	< Back Nest>	
INSIGII DITEIO		a

Windows Driver

4) Select the COM or LPT (Which one you want to use) port to be used and click the "Next" button.

Select a printer and port		BIXOLON
Manufacturer BIXOLON	Printers BIXOLON S BIXOLON S	LP-XXxx0 LP-XXxx3
Serial Port COM1 COM3 COM2 COM4	Paraliel Port © LPT1 © LPT2	USB Port
Network Port	192 . 168 . 1 . 1	Port: 9100
Cancel		Next

Select a printer and port		BIXOLON
Manufacturer BIXOLON	Printers BIXOLON SL BIXOLON SL	P-XXxx0 P-XXxx3
Serial Port COM1 COM3 COM2 COM4	Parallel Port LPT1 LPT2 	USB Port © USB
Network Port	192 . 168 . 1 . 1	Port : 9100
Cancel		Next

5) When the following message box appears, click the "Install" button.



6) Clicking the "Yes" button will reboot the PC.



- 7) Open the printer properties window in the Windows OS.
- 8) Click the "Port Settings" button in the "Ports" tab.

BIXOLON S	LP-XXxx0 Properties		23
Printer Settings General S	Stocks Language haring Ports Adva (OLON SLP-XXxx0	Barcode Fonts Command Fonts anced Color Management S	About Security
Print to the fo checked port	ollowing port(s). Documen	ts will print to the first free	
Port	Description	Finite	
COM/:	Serial Port		
COM5:	Serial Port		
COM3:	Serial Port	DIVOLON, CLD MAND	=
COMI:	Serial Port	BIXOLON SLP-XXXX0	
FILE:	Print to File		
	Virtual printer port for		
038002	virtual printer port for		*
Add P	ort Delete	e Port Configure Port	t
🔽 Enable bid 🥅 Enable prir	irectional support nter pooling		
	ОК	Cancel Apply	Help

Windows Driver

9) Match the communication settings to those of the printer.(The communication settings of the printer can be performed by conducting a self-test.)

COM1 Properties	8 23
Port Settings	
Bits per second: 115200	•
Data bits: 8	•
Parity: None	•
Stop bits: 1	•
Flow control: Hardwa	re 🔻
	Restore Defaults
ОК	Cancel Apply

10) Click the "Print Test Page" button and check printing status.

BIXOLON SLP-XXxx0 Propertie	es 🛛 🕅
Printer Settings Stocks Language General Sharing Ports ////////////////////////////////////	Barcode Fonts Command Fonts About Advanced Color Management Security
BIXOLON SLP-XX	xx0
Location:	
Comment:	
Model: BIXOLON SLP-XX	xx0
Color: No	Paper available:
Staple: Unknown	BIXOLON 1.5 x 1.0 (inch)
Speed: Unknown	BIXOLON 1.5 x 2.0 (inch) BIXOLON 2.0 x 1.0 (inch)
Maximum resolution: 203 dpi	BIXOLON 2.0 x 1.5 (inch)
Pre	eferences Print Test Page
ОК	Cancel Apply Help

11) Proper installation of the driver is indicated if the test page is printed normally.

4-2-2 Via USB Port

- 1) Double-click the Windows Driver installation file.
- 2) Click the "Yes" button



3) Click the "Next" button.

BIXOLON LABEL PRINTER		
BIXOLON LABEL PRINTER	Welcome to the Install Shield Wizard for SLP-XXxx0 Windows driver InstallShield Wizard will install SLP-XXxx0 Windows driver on your computer. To continue, click Next.	
InstallShield	< Back Next> Cance	

4) Select USB and click the "Next" button.

Select a printer and port		BIXOLON
Manufacturer BIXOLON	Printers BIXOLON SL BIXOLON SL	P-XXxx0 P-XXxx3
Serial Port COM1 COM3 COM2 COM4	Parallel Port © LPT1 © LPT2	USB Port USB
Network Port	192 . 168 . 1 . 1	Port : 9100
Cancel		Next

5) When the following message box appears, click the "Install" button.

Windows Security
Would you like to install this device software?
Name: Euro Plus Printers Publisher: BIXOLON Co.,Ltd
Always trust software from "BIXOLON". Install Don't Install
You should only install driver software from publishers you trust. <u>How can I</u> <u>decide which device software is safe to install?</u>

6) Click the "OK" button.



7) Turn on the printer.

J Driver Software Installation		x
Your device is ready to use		
USB Printing Support BIXOLON SLP-XXxx0	Ready to use Ready to use	
		Close

8) The USB Port setting can be confirmed in the Windows Driver properties.

BIXOLON S	SLP-XXxx0 Properties			23
Printer Settings General S	Stocks Language haring Ports Adva	Barcode Fonts anced Color	Command Fonts Management	About Security
Print to the fo	ollowing port(s). Documen	its will print to t	he first free	
Port COM3: COM1: FILE: USB003 USB002	Description Serial Port Serial Port Print to File Virtual printer port for Virtual printer port for	BIXOLON S	LP-XXxx0	E
USB001	Virtual printer port for Standard TCP/IP Port			-
Add P	ort Delete	e Port	Configure Por	t
☑ Enable bid	irectional support nter pooling			
	ОК	Cancel	Apply	Help

Windows Driver

Finiter Settings	Stocks Language	Barcode Font	s Command Fonts	Abou
General Shi	aring Ports	Advanced Co	olor Management	Security
	BIXOLON SLP-XX	xx0		
Location:				
Comment:				
Model: Features	BIXOLON SLP-XX	xx0	able:	
Color: No		Paper availa		
Color: No Double-side	d: No	BIXOLON	1.5 x 1.0 (inch)	*
Color: No Double-side Staple: Unkn	d: No Iown	BIXOLON BIXOLON BIXOLON	1.5 x 1.0 (inch) 1.5 x 1.5 (inch) 1.5 x 2.0 (inch)	^
Color: No Double-side Staple: Unkn Speed: Unkn	d: No Iown Iown	BIXOLON BIXOLON BIXOLON BIXOLON	1.5 x 1.0 (inch) 1.5 x 1.5 (inch) 1.5 x 2.0 (inch) 2.0 x 1.0 (inch)	•
Color: No Double-side Staple: Unkn Speed: Unkn Maximum re	d: No Iown Iown esolution: 203 dpi	BIXOLON BIXOLON BIXOLON BIXOLON BIXOLON	1.5 x 1.0 (inch) 1.5 x 1.5 (inch) 1.5 x 2.0 (inch) 2.0 x 1.0 (inch) 2.0 x 1.5 (inch)	•
Color: No Double-side Staple: Unkn Speed: Unkn Maximum re	d: No Iown Isolution: 203 dpi Pri	BIXOLON BIXOLON BIXOLON BIXOLON BIXOLON BIXOLON	1.5 x 1.0 (inch) 1.5 x 1.5 (inch) 1.5 x 2.0 (inch) 2.0 x 1.0 (inch) 2.0 x 1.5 (inch) Print Test Pag	r ₽

9) Click the "Print Test Page" button and check printing status.

10) Proper installation of the driver is indicated if the test page is printed normally.

4-2-3 Via Network Port

- 1) Double-click the Windows Driver installation file.
- 2) Click the "Yes" button.



3) Click the "Next" button.

BIXOLON LABEL PRINTER		×
BIXOLON LABEL PRINTER	Welcome to the InstallShield Wizard for SLP-XXxx0 Windows driver InstallShield Wizard will install SLP-XXxx0 Windows driver on your computer. To continue, click Next.	
InstallShield	< Back Next > Cance	

- 4) Select Network port.
- 5) Type IP address and port number and then click "Next" button.

Select a printer ar	nd port		BIXOLON
Manufacturer		Printers BIXOLON S BIXOLON S	SLP-XXxx0 SLP-XXxx3
Serial Port © COM1 © COM2	СОМЗ СОМ4	Parallel Port LPT1 LPT2 	USB Port
Network Port Network	IP :	192 . 168 . 1 . 12	23 Port: 9100
Cancel			Next

6) When the following message box appears, click the "Install" button.

Windows Security
Would you like to install this device software?
Name: Euro Plus Printers Publisher: BIXOLON Co.,Ltd
Always trust software from "BIXOLON". Install Don't Install
You should only install driver software from publishers you trust. <u>How can I</u> <u>decide which device software is safe to install?</u>

7) Clicking the "Yes" button will reboot the PC.



- 8) Open the printer properties window in the Windows OS.
- 9) Click the "Port Settings" button in the "Ports" tab.

BIXOLON SL	P-XXxx0 Properties			23
Printer Settings General Si	Stocks Language I haring Ports Adva DLON SLP-XXxx0	Barcode Fonts anced Color	Command Fonts Management	About Security
Print to the fo	llowing port(s). Documen	ts will print to t	he first free	
Port	Description	Printer		
USB002	Virtual printer port for			
USB001	Virtual printer port for			
192.16	Standard TCP/IP Port			
✓ IP_192	Standard TCP/IP Port	BIXOLON S	SLP-XXxx0	
P_192	Standard TCP/IP Port			=
IP_192	Standard TCP/IP Port			
XPSPort:	Local Port			-
Add Po	Delete	Port	Configure Por	t
🔽 Enable bidi 🥅 Enable prir	irectional support iter pooling			
	ОК	Cancel	Apply	Help

10) Match the communication settings to those of the printer.

Configure Standard TCP/IP Port	Monito	r	23
Port Settings			
Port Name:		IP_192.168.1.123	
Printer Name or IP Address:		192.168.1.123	
Protocol			
Raw		C LPR	
Raw Settings			
Port Number:	9100		
LPR Settings			Ξ.
Queue Name:			
LPR Byte Counting Ena	abled		
SNMP Status Enabled			
Community Name:	public		
SNMP Device Index:	1		ן ו
		OK Car	ncel

11) Click the "Print Test Page" button and check printing status.

BIXOLO	N SLP-XXxx	0 Propert	ies			23
Printer Setting	gs Stocks	Languag	ge Barcode	Fonts	Command Fonts	About
General	Sharing	Ports	Advanced	Color	Management	Security
	BIXOL	ON SLP-X	Xxx0			
Location:						
Comment:						
Model:	BIXOL	ON SLP-X	Xxx0			
Color: N	lo		Papera	availabl	e:	
Double-	sided: No		BIXOL	.ON 1.5	x1.0 (inch)	*
Staple: U	Jnknown		BIXOL	.ON 1.5	x 1.5 (inch) x 2.0 (inch)	
Speed: L	Jnknown		BIXO	ON 2.0	x1.0 (inch)	
Maximu	m resolution	: 203 dpi	BIXO	.ON 2.0	x1.5 (inch)	*
		F	Preferences		Print Test Pa	ige
		OK	Cance		Apply	Help

12) Proper installation of the driver is indicated if the test page is printed normally.

5. Detailed Windows Driver Settings

5-1 Printing Preferences

Barcode Fonts				Command Fonts		
Custom	Commands Import/			Export :	settings	About
Options	Advanced	Setup	Dithe	ing	Stocks	Printer Memory
Settings						
No. Of Copies: 1						
S	peed:		6		• "/s	
Darkness:			14		- -	
St	tocks:		User def	ined		•
Paper For	nat					
C) cm			or	trait	
C) mm		enva	🔘 land	dscape	
C) inch		VBCL	📃 rota	te 180°	
Paper Size	;					
W	/idth:	4.00]		
Н	eight:	6.00]		
Unprintabl	e Area ——					
Le	eft:	0.00		Top:	().00
R	ight:	0.00		Bottor	n: (0.00

1	No. Of Copies	The number of copies	
2	Speed	Set the printing speed	
3	Darkness	The darkness level of printouts.	
4	Portrait	The printer prints in portrait orientation.	
5	Landscape	The printer prints in landscape orientation.	
6	Rotate 180	The option of rotation 180 degree.	
7	Width	Set the width of the paper.	
8	Height	Set the height of the paper.	
9	Unprintable Area	Set the unprintable area.	

Windows Driver

5-2 Adding new paper size

1) Click the "Preferences..." button

BIXOLON SLP-XXxx0 Properties				
Printer Settings Stocks Language General Sharing Ports A	Barcode Fonts Command Fonts Ab	out		
BIXOLON SLP-XXX	x0			
Location:				
Comment:				
Model: BIXOLON SLP-XXx Features	x0			
Color: No Double-sided: No	Paper available:			
Staple: Unknown	BIXOLON 1.5 x 1.0 (inch)			
Speed: Unknown	BIXOLON 1.5 x 2.0 (inch) BIXOLON 2.0 x 1.0 (inch)			
Maximum resolution: 203 dpi	BIXOLON 2.0 x 1.5 (inch)			
Preferences Print Test Page				
OK Cancel Apply Help				

2) Click the "New" button.

BIXOLC	ON SLP-XXxx0 Prir	nting Prefer	ences	23		
	Barcode Fonts		Command Fonts			
Custom	Commands	Import/Export	port/Export settings Abor			
Options	Advanced Setup	Dithering	Stocks	Printer Memory		
Defined stocks						
	3XOLON 1.5 x 1.0 (md 3XOLON 1.5 x 1.5 (md 3XOLON 1.5 x 2.0 (md 3XOLON 2.0 x 1.0 (md 3XOLON 2.0 x 1.5 (md 3XOLON 2.0 x 2.0 (md 3XOLON 2.0 x 3.0 (md 3XOLON 2.0 x 4.0 (md 3XOLON 2.0 x 5.0 (md 3XOLON 2.0 x 6.0 (md 3XOLON 2.0 x 7.0 (md	#) #) #) #) #) #) #) #) #) #)		E		
Stock description						
Description Define your own label stock here and save it for future use. Each stock stores label dimensions and some printer settings.						
New Change Delete						
	ОК	Cancel	Apply	Help		

3) Set a value you want and then click "OK" button.

Define St	ock					ନ୍ତ	23
Name -							
	BIXOLON 1.5	BIXOLON 1.5 x 1.0 (inch)					
Options							
	Darkness		17	•			
	Speed		5	•	"/s		
Dimensi	ons						
	Label Width		1.50		inch		
	Label Height		1.00		inch		
Unprinta	able Area ——						
	Left:	0.00		Top:		0.00	
	Right:	0.00		Bottom:		0.00	
	ОК		Cano	el		Help	

6. Specifications

6-1 Resolution

Resolution	203 dpi	300 dpi
	SLP-TX220	SLP-TX223
	SLP-TX420	SLP-TX423
	SLP-TX400	SLP-TX403
	SLP-DX220	SLP-DX223
	SLP-DX420	SLP-DX423
Madal Nama	SLP-DL410	SLP-DL413
Model Name	SLP-T400	SLP-T403
	SLP-T400R	SLP-T403R
	SLP-D220	SLP-D223
	SLP-D420	SLP-D423
	SRP-770III	
	SRP-770II	

6-2 Paper Size

1.5 x 1.0 inch (38.1 x 25.4 mm) 1.5 x 1.5 inch (38.1 x 38.1 mm) 1.5 x 2.0 inch (38.1 x 50.8 mm) 2.0 x 1.0 inch (50.8 x 25.4 mm) 2.0 x 1.5 inch (50.8 x 38.1 mm) 2.0 x 2.0 inch (50.8 x 50.8 mm) 3.0 x 1.0 inch (76.2 x 25.4 mm) 3.0 x 1.5 inch (76.2 x 38.1 mm) 3.0 x 2.0 inch (76.2 x 50.8 mm) 3.5 x 1.0 inch (88.9 x 25.4 mm) 3.5 x 1.5 inch (88.9 x 38.1 mm) 3.5 x 2.0 inch (88.9 x 50.8 mm) 3.5 x 3.0 inch (88.9 x 76.2 mm) 3.5 x 4.0 inch (88.9 x 101.6 mm) 3.5 x 6.0 inch (88.9 x 152.8 mm) 4.0 x 1.0 inch (101.6 x 25.4 mm) 4.0 x 1.5 inch (101.6 x 38.1 mm) 4.0 x 2.0 inch (101.6 x 50.8 mm) 4.0 x 3.0 inch (101.6 x 76.2 mm) 4.0 x 4.0 inch (101.6 x 101.6 mm) 4.0 x 6.0 inch (101.6 x 152.8 mm) 4.0 x 8.0 inch (101.6 x 203.2 mm) 4.0 x 12.0 inch (101.6 x 304.8 mm)